

MiniLab 37



Live

MiniLab 37 Presentation	2
General layout	2
Setting up your unit	3
Script features	4
Knobs and Faders	4
Pads	5
Analog Lab Mode	6

_MiniLab 37 Presentation

General layout:



This guide highlights a script that integrates the MiniLab 37 into Ableton Live.

1. Setting up your unit


You'll need the latest version of Live to be able to use the Integration script for MiniLab 37.

If you manage to install the latest version of Live, here are the steps:

- Connect your MiniLab 37 and select DAW program [shift + pad 3].
- Open Live.
- The MiniLab 37 should automatically be detected and ready to use.

If the MiniLab 37 is not detected:

- Go to Live MIDI settings [Options / Preferences / Link Tempo MIDI tab]
- In the MIDI part, select your control surface [MiniLab 37]
- Set the right In and out Port ["MiniLab 37 MIDI" / "MiniLab 37 MIDI"]



- The MiniLab 37 should be detected and ready for Live.

2. Script features

a. Knobs and Faders

Main encoder:

Actions:

Navigates in the scenes [Scene view]

Navigates in the timeline [Arrangement view]

Feedback:

The content is displayed on MiniLab 37's screen

Main encoder click:

Actions:

Launches the whole scene [Scene view]

Launches the arrangement [Arrangement view]

Knobs 1 → 8 and faders 1 → 4:

Actions:

Knobs control some parameters of the current armed plugin

Faders control volume, send A/B and pan

Feedback:

Display the parameter name and value on MiniLab 37's screen

Shift + Main encoder:

Actions:

Navigates in the tracks

Feedback:

The content is displayed on MiniLab 37's screen

Shift + Main encoder click:

Actions:

Arm the selected track

Feedback:

Arm pictogram is displayed on MiniLab 37's screen

b. Pads

There are 8 physical pads on the MiniLab 37. Each pad has a different function, with 2 banks to work with [A / B]:




You can switch between the 2 banks by entering "Pad Mode" [Shift + Pad 2].

Bank A:

Action:

Trigger some clips on the scene view



Feedback:

The bank A LED color will match the color of the selected scen

Bank B:

Actions:

Pressing the pads will triggers sounds

The Drum Machine plugin is already mapped. You can browse your sound with the main encoder.



Feedback:

The Pad LEDs match the one you selected in the plugin for your sounds

Shift + Pad 4/8:

Actions:

Orange Pad: Loop

Green Pad: Play/Pause - blink if on play

White Pad: Stop

Red Pad: Record - blink if on record


White Pad 2: Tap Tempo

Feedback:

The bank A LED color will match the color of the selected scen

C. Analog Lab Mode

If you are using Analog Lab, make sure you link the correct device when you open the plugin.



You can enter Analog Lab Mode to have perfect control over Analog Lab by selecting the Arturia program on MiniLab 37.

When Analog Lab is selected, you can manage the plugin as you would do in standalone [Navigation, selection and FX].